## UNIT-IV Microbial assay



## RASMITA JENA ASSISTANT PROFESSOR SoPLS, CUTM, BBSR

Principles and methods of different microbial assay

## Introduction

- The microbiological or microbial assay is a type of biological assay in which the relative potency of activity of a compound is determined by measuring the amount required for producing the predicted effect on a suitable test organism under standard conditions.
- The microbiological assay is a biological assay performed using microorganisms, e.g., **bacteria**, **yeast**, **and moulds**.
- These assays are much easier than those performed using mammals for isolating essential vitamin; for example, a growth factor for *Lactobacillus* proved to be similar to a hematopoietic factor in pernicious anemic patients.

- Many therapeutic agents, such as antibiotics inhibiting microbial growth or the essential growth factors (vitamins and amino acids), are standardized by microbiological assays.
- The activity of antibiotics (extent of inhibiting the microbial growth), vitamins, or amino acids (extent of supporting the microbial growth) is determined by microbiological assays; while the potency (concentration or amount) of such substances is determined by chemical assays.
- Thus, microbiological assays of antibiotics, vitamins, and amino acids are significantly important.

## Principles

- A microbiological assay relies on the principle that when certain compounds are present in limited amounts, the amount of microbial growth corresponds to the amount of these compounds.
- The basic procedure of most of the microbial assays is same; however, the test conditions vary.
- The test substance is added to a liquid or gel medium, test microorganism is inoculated on the medium, and the resultant response (which depends on the substance's biochemical effect on the test organism) is observed.

- It may be a growth response (positive in the assay of nutrients and negative in the assay of antibiotics), which is determined by counting, optical density, weight, or area; the growth response may be a definite end-point, or an all-or none response.
- In case of either a positive or negative metabolic response, the metabolic products or changes in some function may be measured. Examples of some measurable metabolic responses are acid production, CO2 production, oxygen uptake, nitrate reduction, haemolysis of RBCs, anti luminescent activity, or inhibition of spore germination.
- Substances analogous and antagonistic to regular metabolites inhibit the growth of wild, prototrophic strains of bacteria. The nutrilite content can be assayed by adding graded amounts of nutrilite for re-activating the growth.

**Merits:** A microbiological assay has the following merits:


- 1)It is **suitably used** for compounds which cannot be assayed by either **physical or chemical methods**.
- 2) It is used for the assay of **naturally occurring therapeutic agents**.
- 3) It minimizes the mortality rate of animals.
- 4) It is a simple and rapid method as compared to bioassays.
- 5) It is used for accurate standardization of medicinal compounds.
- 6) It determines the concentration as well as activity of compounds.
- 7) It does not require large amount of sample and instruments.
- 8) Its complete procedure can be automated to minimize the duration.


**Demerits:** A microbiological assay has the following demerits:

- 1) It requires a **specific test organism** for the assay of a **particular compound.**
- 2) It **demands maintenance of sterile conditions** within the laboratory.
- 3) It may give invalid results due to a slight variation in incubation temperature.
- 4) It is a **time-consuming method**.
- 5) It requires well trained and expert individuals.

**Standardization of Antibiotics/ Microbiological Assay of Antibiotics** 

- The microbiological assay of an antibiotic is based upon a comparison of the inhibition of growth of microorganisms by measured concentrations of the antibiotics under examination with that produced by known concentrations of a standard preparation of the antibiotic having a known activity.
- Two general methods are usually employed, i.e.,
  - Cylinder-plate (or cup plate) method
  - Turbidometric (or tube assay) method.





- The cylinder-plate method (Method A) depends upon diffusion of the antibiotic from a vertical cylinder through a solidified agar layer in a Petri dish or plate to an extent such that growth of the added micro-organism is prevented entirely in a zone around the cylinder containing a solution of the antibiotic.
- The Turbidometric method (Method B) depends upon the inhibition of growth of a microbial culture in a uniform solution of the antibiotic in a fluid medium that is favorable to its rapid growth in the absence of the antibiotic.